

Export Plug-in from Vectorworks 2019 to Artlantis 6.5 & 7.0

Export Plug-in from Vectorworks 2019 to Artlantis 2019

Artlantis export version: 24.1.2

1- Introduction

2- Plug components and installation instruction

3- Launch VectorWorks

4- Limitations and warnings

5- More informations about Artlantis

1- Introduction

Artlantis 6 plug 24.1.2 exports in .atl file format to Artlantis versions 6.5 & 7.0

Minimum required: Vectorworks 2019 and Artlantis 6.5

Artlantis 2019 plug 24.1.2 exports in .atl file format to Artlantis 2019

Minimum required: Vectorworks 2019 and Artlantis 2019

2- Plug component and installation instructions

Mac platform:

Component:

One folder: **Artlantis Export**

Installation:

Put **Artlantis Export** folder into the **Plug-Ins*** folder of Vectorworks.

* Important:

1- The **Artlantis Export** folder **must** be placed into the **Plug-Ins** folder.

2- Copy the entire **Artlantis Export** folder. Do not copy elements separately.

3- Do not keep or rename an old **Artlantis Export** folder.

Windows platform:

Components:

Four files **AbventTools-Release-x64-MSVC12.dll**, **AbventXML-Release-x64-MSVC12.dll**, **CAtI6.5.dll** & **CAtI8.dll** and one folder **Artlantis Export**.

Installation:

1- Put the files **AbventTools-Release-x64-MSVC12.dll**, **AbventXML-Release-x64-MSVC12.dll**, **CAtI6.5.dll** & **CAtI8.dll** at the first level of the Vectorworks folder

2- Put **Artlantis Export** folder into the **Plug-Ins*** folder of Vectorworks.

*Important:


1- The **Artlantis Export** folder **must** be placed in the **Plug-Ins** folder.

2- Copy entirety **Artlantis Export** folder. Do not copy the elements separately.

3- Do not keep or rename an old **Artlantis Export** folder.

3- Launch Vectorworks


In Vectorworks display the Workspace Editor by choosing the command **Tools > Workspaces > Edit Current Workspace**



Click on the **Menus** thumbnail, the left column displays the list of **Commands**, and the right column the lists of **Menus**.

- In the right column, click on **the arrow** in front of **File** then click on the arrow in front of **Export**.
- in the left column, click on the arrow in front Of **Import/Export**.
- Select the **Artlantis Export...** item then drag and drop it to the right column just under the item **Export**. Click **OK** to validate and close the dialog.

Then check that the new command is available in menu **File > Export > Artlantis Export**.



4- Limitations and warnings

Please do not use older plug-ins with VectorWorks 2019 as they are not compatible. They might interfere with the new plug-in.

5- More information and updates...

Contact Us!

Please feel free to contact Abvent, or the worldwide partner network, for further information!

To find your nearest Artlantis reseller or distributor, please visit the www.artlantis.com/partners website!

In case you need any technical support regarding Artlantis, please contact the Artlantis Support Center at www.artlantis.com

Abvent

58 rue Saint-Lazare

75009 Paris

France

Phone: +33 1 53010505

E-mail: international@abvent.com

Web: www.artlantis.com

©2019 Abvent

www.abvent.com All rights reserved. Artlantis is a registered trademark of Abvent. Other product and company names are trademarks of the respective holders.

Abvent May 2019