

# Export Plug-in from Vectorworks 2016 to Artlantis 5 & 6.5

Artlantis export version: 21.1.0

- 1- Introduction**
- 2- Plug component and installation instructions**
- 3- Launch VectorWorks**
- 4- Limitations and warnings**
- 5- More information about Artlantis**

---

## 1- Introduction

Artlantis plug 21.1.0 exports in .atl file format to Artlantis versions 5 or 6.5  
Minimum required: Vectorworks 2016 and Artlantis 5 or 6.5

---

## 2- Plug component and installation instructions

### Mac platform:

#### Component:

One folder: **Artlantis Export**

#### Installation:

Put **Artlantis Export** folder into the **Plug-Ins\*** folder of Vectorworks.

\* Important:

- 1- The **Artlantis Export** folder **must** be placed into the **Plug-Ins** folder.
- 2- Copy integrally **Artlantis Export** folder. Do not copy the elements separately.
- 3- Do not keep or rename an old **Artlantis Export** folder.

### Windows platform:

#### Component:

Two files **Catl5\_64.dll** and **Catl6.5.dll** and one folder **Artlantis Export**.

#### Installation:

- 1- Put the files **Catl5\_64.dll** and **Catl6.5.dll** at the first level of the Vectorworks folder
- 2- Put **Artlantis Export** folder into the **Plug-Ins\*** folder of Vectorworks.

\* Important:

- 1- The **Artlantis Export** folder must be placed in the **Plug-Ins** folder.
- 2- Copy integrally **Artlantis Export** folder. Do not copy the elements separately.
- 3- Do not keep or rename an old **Artlantis Export** folder.

### 3- Launch Vectorworks

In Vectorworks display the Workspace Editor  
Please refer to the Vectorworks documentation.

Choose among one of the 3 displayed options.

The Workspace Editor dialog is displayed.  
Click on the **Menus** thumbnail the left column displays the list of the **Commands**, and the right column the lists of the **Menus**.

- In the right column, click on **the arrow** in front of **File** then click on the arrow in front of **Export**.
  - in the left column, click on the arrow in front of **Import/Export**.
  - Select the **Artlantis Export...** item then drag and drop it to the right column just under the item **Export**.\*.
- Click **OK** to validate and close the dialog.

Then check that the new command is available menu **File > Export > Artlantis Export**.

### 4- Limitations and warnings

Please do not use older plug-ins with VectorWorks 2016 as they are not compatible. They might interfere with the new plug-in.

### 5- More information and updates...

Contact Us!

Please feel free to contact Abvent, or the worldwide partner network, for further information!

To find your nearest Artlantis reseller or distributor, please visit the [www.artlantis.com/partners](http://www.artlantis.com/partners) website!

In case you need any technical support regarding Artlantis, please contact the Artlantis Support Center at [www.artlantis.com](http://www.artlantis.com)

Abvent

58 rue Saint-Lazare  
75009 Paris  
France  
Phone: +36 1 437 3261  
Fax: +36 1 437 3268  
E-mail: [international@abvent.com](mailto:international@abvent.com)  
Web: [www.artlantis.com](http://www.artlantis.com)

©2017\_Abvent\_www.abvent.com All rights reserved. Artlantis is a registered trademark of Abvent. Other product and company names are trademarks of the respective holders.

Abvent January 2017